

Pacer Pro - Setup Guide

Independent guide for installing, activating, and recovering the Pacer Pro desktop extension package.

Pacer Pro includes the core reading-assistance functions of Pacer plus licensed Pro features activated after purchase.

1. System Requirements

Use this guide only for the environment below.

- Desktop browser only. This guide is for the manually loaded Pacer Pro package. It does not cover mobile browsers.
- **Recommended browser:** current stable Google Chrome for desktop.
- **Browser platform requirement:** a Manifest V3-capable Chromium browser. This package uses Manifest V3.
- **Operating system for current Chrome:** Windows 10 or later, or macOS 12 Monterey or later.
- **Optional alternative:** current stable Microsoft Edge (Chromium-based).
- **Email access:** required to receive the license key after purchase and the one-time verification code used during activation.
- **Internet access:** required during initial activation and later license checks.
- **Scope of this guide:** no promise is made for beta, dev, canary, mobile, Linux, ChromeOS, or future browser or OS releases.

2. Installation Steps

Download and unzip the package

1

Download **pacер-pro.zip** and unzip it to a folder you can keep on your computer.

Do not delete or move the extracted folder after installation, because the browser loads the extension from that location.

2

Open the extensions page

In Google Chrome, open **chrome://extensions/** in the address bar.

3

Turn on Developer mode

Enable **Developer mode** at the top right of the extensions page.

4

Load the unpacked folder

Click **Load unpacked** and select the extracted Pacer Pro folder.

5

Pin the extension for easier access

Pin Pacer Pro from the browser toolbar so the popup and options are easier to open during activation.

3. License Activation

- First, click the Pacer Pro extension icon in the browser toolbar.
- Open the Pacer Pro popup or options screen from the browser toolbar.
- Enter the purchase email address and the license key sent after checkout.
- Request the one-time verification code and enter it exactly as received by email.
- Current license policy: up to 5 activations per license.
- Keep the purchase email and license email for later recovery or support.

4. Basic Usage

- Start or stop Pacer with Alt+R. On macOS keyboards, this is typically Option+R.
- Adjust pace with Alt+Up and Alt+Down. On macOS keyboards, this is typically Option+Up and Option+Down.
- Switch modes with Alt+M. On macOS keyboards, this is typically Option+M.
- Open the popup or options screen when you need to check activation status or manage Pro settings.

5. Troubleshooting

- If activation fails, confirm that the purchase email address and license key exactly match the license email, then check the inbox or spam folder for the OTP message.
- If Pro features do not appear after successful activation, refresh or reopen the page and confirm the license status in the popup or options screen.
- If the activation limit has been reached, deactivate an unused installation or contact support using the purchase email address.
- Browser internal pages and some managed or security-restricted environments may block overlays, shortcuts, or other extension behavior.

6. Recovery Note

This guide is limited to the current desktop package and current license workflow. Browser vendor changes, managed-device restrictions, or unsupported platforms may require a different setup path.